

## Device: Panasonic PTZ



### Compatibility

With our Panasonic PTZ Device Core we currently have comprehensive support for the:


- AW-UE150
- AW-HE130
- AW-HE120
- AW-UE100
- AW-UE70/AW-UN70
- AW-HE50
- AW-HE42
- AW-HE40
- AK-UB300

The complete lineup are not supported as the protocol varies for each model. We have integrated with the models we have had a high demand for and/or have had a chance to integrate with. For cameras *not* on the above list just basic pan, tilt, zoom and preset functionality are integrated as the protocol remains the same for these features across all models.

Mature



**Panasonic PTZ**  
Controls Panasonic AW-HEx series robotic cameras over IP. Currently, comprehensive support for AW-HE130, AW-HE120, AW-UE70/AW-UN70, AW-HE50, AW-HE40 is available, while other models have basic PTZ and preset functionality. [See Panasonic PTZ Action Manual](#)



Description of the Panasonic PTZ Device Core from <https://www.skaarhoj.com/support/device-cores/>

### Note about AWB Exec

Notice when an auto white balance is executed the controller will momentarily loose connection to the camera, as the camera stops responding during this process.

### Note about Panasonic AW-HN130

We have not tested the AW-HN130 but many have reported that we are able to control the camera similar to the AW-HE130. However, AW-HN130 firmware v.2.38 has been known to cause the controller to freeze. We do not recommend running your camera with that firmware version at this time.

**Note about Panasonic UE100s + UE150s**

Since our Panasonic device core is able to connect to a large variety of models from a single device core, it has gotten very large. For this reason after v2.5.6, it is no longer possible to control 8x cameras from a single device core but only 7x. If there is no need to control the UE100, then rolling back to v2.5.6 will allow for a connection to 8x cameras from a single core. Additionally after v2.5.6, it is no longer possible to connect to more than 3x UE150s at any one time. Unfortunately the effect that this has had causes the controller to freeze up. Please check the Installation and Operations Manual for instructions on rolling back to an earlier firmware.

The size of the core also makes it important to limit the number of other connected devices as this can overwhelm the processor board and memory. The best way to determine where the limit is, is to build up the configuration slowly one device core at a time. We are working on a solution, though we are no sure if that will be within the UniSketch platform or only on Reactor/Blue Pill.

## Device Configurations

Device configuration options exist:

- Index 0: **Connect Timeout in ms**
- Index 1: **Reply Timeout in ms**
- Index 2: **IPs for Camera Groups**
- Index 3: **Time between each parameter query request PER camera in ms**

### Connect + Reply Timeout

Default Connect Timeout = 100 ms. Timeout for the camera to accept the TCP connection.

Default Reply Timeout = 200 ms. When connection have been accepted, the reply timeout is the time the controller waits for a reply.

In general increasing timeouts will decrease responsive but increase connection stability. The default values have been chosen based on tests at our facility but is not necessarily suitable for all cases.

### Camera Groups

Index 2 have the following structure:

```
D0:2="[xxx.xxx.xxx.xxx, yyy.yyy.yyy.yyy, ....],[zzz.zzz.zzz.zzz]"
```

This enables camera groups. Notice the outer quotes ", if there's an error in this device core option it will fallback to the regular configured IP address. The format is such that each group is an array separated by a comma ,. Inside each group it's also just simple ip addresses separated by a comma ,. There's not any limit to the IPs per group but the system won't handle anything more than 8 per group. There's no limit to the number of groups besides the maximum 13 in the frontend. See example 3 for use case.

### Parameter query requests

Default time between *each* parameter query request *per* camera = 1500 ms. To begin with a controller will query all parameters for all cameras connected to a controller. Thereafter a controller will only query parameters updates from the camera on a 1.5 s interval between query requests per camera. This parameter is set to 1.5 seconds to improve connection stability when either:

- Two (or more) SKAARHOJ controllers are connected to the same camera
- A SKAARHOJ controller *and* a Panasonic controller is connected to the same camera
- A SKAARHOJ controller and the web interface is used to control the same camera


This means if a parameter is changed on SKAARHOJ controller #1 it will not be instantly reflected on SKAARHOJ controller #2, or the Panasonic controller, or the web interface. It also means if a change is made on the Panasonic controller or the web interface it will not be instantly reflected on the SKAARHOJ controller. The parameter query time have been implemented to support cases where one operator is in charge of PTZ control (controller #1) while another operator is in charge shading control (controller #2).

The time can be lowered if you have less complex setups and want faster responds on the connected units. See example 4 for use case.

## Example 1:

Setting "Reply Timeout" to 250 ms could look like this device configuration code: "D0:1=250" where the general form would be "Dx:y=z" where "x" is the number of the device core as installed on the controller (starting with zero for the first device core), "y" the index number and "z" the value for that index.


To confirm that a device configuration is in fact detected by the controller, please check it out on the serial monitor where it will be mentioned:



Example: If the Panasonic PTZ device core is the first like below:

## Device Cores


Below, you can see the currently enabled device support on your controller. You can add and delete device cores in accordance with your requirements up to a maximum of 14 devices. To understand the development states Mature, Beta, Alpha and Planned (as well as Pro and Planned actions), please check out the [device core support page](#). For general documentation, please see the [UniSketch Manual](#) and [System Actions Manual](#).



Then setting the "Connect Timeout" would be set by this configuration under "Manage Media" on your configuration page for your controller on [cores.skaarhoj.com](http://cores.skaarhoj.com)

## Manage Media

Here, you can add various types of media content to your configuration.



**Example 2:**

Setting “Connect Timeout” to 200 ms and “Reply Timeout” to 250 ms could look like this device configuration code

```
D0:0=200,1=250
```

## Manage Media

Here, you can add various types of media content to your configuration.

Panasonic PTZ ▾

### Device Core Options

Some device cores support additional options that can be defined through this text field. Please refer to the manual for the particular device core for details.

D0:0=200,1=250


### Strings

Add String

### Images

Save Settings

Add Image



**Example 3:**

Setting "Groups IPs" could look like this device configuration code


```
D0:2="[192.168.10.100, 192.168.10.101, 192.168.10.102, 192.168.10.103, 192.168.10.104,
192.168.10.105, 192.168.10.106, 192.168.10.107],[192.168.10.109, 192.168.10.110, 192.168.10.111,
192.168.10.112, 192.168.10.113, 192.168.10.114, 192.168.10.115, 192.168.10.116]"
```

Where

Group 1 have IPs 192.168.10.100 to 192.168.10.107

Group 2 have IPs 192.168.10.109 to 192.168.10.116


To confirm that a device configuration is in fact detected by the controller, please check it out on the serial monitor where it will be mentioned:

**Example 4:**

Setting "parameter query request PER camera" to 1000 ms could look like this device configuration code

```
D0:3=1000
```

To confirm that a device configuration is in fact detected by the controller, please check it out on the serial monitor where it will be mentioned:



An excerpt of the list of Panasonic PTZ related actions.

*Notice some actions are camera dependent. Please check the camera manual/protocol if specific actions are supported for your type of camera*

Panasonic PTZ: Pan  
 Panasonic PTZ: Tilt  
 Panasonic PTZ: Pan/Tilt  
 Panasonic PTZ: Zoom  
 Panasonic PTZ: Zoom (Binary)  
 Panasonic PTZ: Auto Focus  
 Panasonic PTZ: Focus  
 Panasonic PTZ: Creep Focus (AK-UB300)  
 Panasonic PTZ: Focus One Push  
 Panasonic PTZ: Auto Iris  
 Panasonic PTZ: Iris  
 Panasonic PTZ: Sensor Gain  
 Panasonic PTZ: Shutter  
 Panasonic PTZ: Synchro-Scan  
 Panasonic PTZ: Auto Shutter Limit  
 Panasonic PTZ: Shutter Mode  
 Panasonic PTZ: Shutter SW (Ak-UB300)  
 Panasonic PTZ: Scene File  
 Panasonic PTZ: AWB Mode  
 Panasonic PTZ: AWB Exec  
 Panasonic PTZ: ABB Exec  
 Panasonic PTZ: Master Pedestal  
 Panasonic PTZ: WB R/B Gain  
 Panasonic PTZ: Pedestal R/G/B  
 Panasonic PTZ: Pedestal Offset (AW-UE150)  
 Panasonic PTZ: Detail  
 Panasonic PTZ: Advanced Detail  
 Panasonic PTZ: Contrast Level  
 Panasonic PTZ: Color Temperature  
 Panasonic PTZ: ND Filter  
 Panasonic PTZ: Chroma Level  
 Panasonic PTZ: Chroma Phase (AW-UE150)  
 Panasonic PTZ: DRS  
 Panasonic PTZ: Knee Mode  
 Panasonic PTZ: Auto Knee Response  
 Panasonic PTZ: Knee Point  
 Panasonic PTZ: Knee Slope  
 Panasonic PTZ: Preset


Panasonic PTZ: Preset Speed  
 Panasonic PTZ: Set Tally  
 Panasonic PTZ: Audio Control  
 Panasonic PTZ: Audio Volume  
 Panasonic PTZ: Output Format  
 Panasonic PTZ: Zoom Pan/Tilt Speed Adjust  
 Panasonic PTZ: Invert PTZ Control  
 Panasonic PTZ: Install Position  
 Panasonic PTZ: UHD Crop - Mode (AW-UE150)  
 Panasonic PTZ: UHD Crop - SDI Out Select  
 Panasonic PTZ: UHD Crop - IP Out  
 Panasonic PTZ: UHD Crop - Marker Select  
 Panasonic PTZ: UHD Crop - Output Select  
 Panasonic PTZ: UHD Crop - H Adjust  
 Panasonic PTZ: UHD Crop - V Adjust  
 Panasonic PTZ: OSD Menu  
 Panasonic PTZ: OSD Menu Navigation  
 Panasonic PTZ: OSD Menu Mix  
 Panasonic PTZ: Night Mode On/Off  
 Panasonic PTZ: Night Mode Selection  
 Panasonic PTZ: Night Mode Level  
 Panasonic PTZ: PTZ Cruise Control  
 Panasonic PTZ: PTZ Trace  
 Panasonic PTZ: Power  
 Panasonic PTZ: Speed Limit  
 Panasonic PTZ: Camera Select  
 Panasonic PTZ: Camera Group Select

## Tally

In some cases it can be desirable to route tally to the PTZ cameras based on tally from a video switcher. This can to some degree be done from the hardware interface often called "Controller" on our panels. This interface is constantly evaluated. There is a limit to how many actions can be assigned onto this interface, but we are working on a way to expand this.

In the case of a PTZ Fly and ATEM Tally it would be done the following way:

- Add the ATEM Device Core and set IP Setting



- On the Controller Interface add the below actions. This instructs the system to enable tally on Cam 1-4 based on ATEM Program 1-4 . The mapping can be differently.

#15 **Controller** Controller

**Normal**

BMD ATEM: Program Src	M/E 1	1	Hold Down
and	System: Synthesized Trigger	Binary	Prev. action
and	Panasonic PTZ: Set Tally	Cam 1	Hold Down
and	BMD ATEM: Program Src	M/E 1	2
and	System: Synthesized Trigger	Binary	Prev. action
and	Panasonic PTZ: Set Tally	Cam 2	Hold Down
and	BMD ATEM: Program Src	M/E 1	3
and	System: Synthesized Trigger	Binary	Prev. action
and	Panasonic PTZ: Set Tally	Cam 3	Hold Down
and	BMD ATEM: Program Src	M/E 1	4
and	System: Synthesized Trigger	Binary	Prev. action
and	Panasonic PTZ: Set Tally	Cam 4	Hold Down



### **AK-UB300 Notes**

For the AK-UB300 integration the following actions have been implemented:

- Iris
- Auto iris
- AWB execute
- ABB execute
- Pedestal
- Pedestal R/B
- Shutter SW
- Shutter
- Shutter Mode
- Gain R/B
- Format
- ND Filter
- Scene

The following list has been implemented but not tested fully:

- Knee mode
- Auto Knee response
- Knee Point
- Knee slope
- Chroma level
- Contrast

The following list is NOT working:

- Zoom (Implemented, sends right commands, camera responds with OK but no change in zoom)
- Focus (Not implemented. Tested commands in browser, camera responds OK but no change in focus)
- Color temp